

Finding Your MAC (Ethernet) Address All Device Types

Standard Operating Systems

WINDOWS 7

1. Open a **Command Prompt**:
 - a. Click the **Start** button.
 - b. In the **Search programs and files** box, type **cmd** and press **Enter** or **Return** on your keyboard.
2. Type **getmac** at the command prompt. This will show your MAC address for your network adapter.
 - a. If you have more than one network adapter, such as a laptop that has both Wi-Fi and Ethernet connections, use the command **getmac /v /fo list** to get an organized list.
 - b. Occasionally, the **getmac** command will stall or not work on your installation. In that case, using the command **ipconfig** will also provide that information. The MAC address will be listed as a **Physical Address** for each of your Network Connections.
3. Type **exit** to close.

WINDOWS 8

1. Open a **Command Prompt**:
 - a. On the **Start** page, start type **cmd**.
 - b. In the **Search** window, click **Command Prompt**.
2. Type **getmac /v** at the command prompt. This will show your MAC address for your network adapter (listed as Physical Address). For the Wi-Fi, look for the Wi-Fi line.
 - a. Occasionally, the **getmac** command will stall or not work on your installation. In that case, using the command **ipconfig** will also provide that information. The MAC address will be listed as a **Physical Address** for each of your Network Connections.
3. Type **exit** to close.

MAC OS X

1. Launch **System Preferences** from the **Dock**.
2. Choose **Network** from the **Internet and Wireless** section.
3. Select your Network adapter (**Ethernet** or **Wi-Fi**) and click **Advanced**.
4. Click the **Hardware** tab.
5. Your Mac Address will be listed at the top of this page.

LINUX

1. Open a **terminal** or **console window**.
2. Type **ifconfig**.
3. The MAC address will be listed as **HWaddr** in the format of 12:34:56:78:AB.

CHROMEBOOK

1. Open the **Chrome** browser.
2. Enter **chrome://system** in the address field.
3. Expand the **ifconfig** field.
4. In the **wlan0** section, you'll find the MAC address listed as **Ethernet HWaddr**.

WReaders and Tablets

KINDLE FIRE

1. From your home screen, tap your **Settings** icon.
2. Tap on **More**, and then tap on **Device**.
3. Scroll down to find the **Wi-Fi MAC Address** section.

KINDLE, KINDLE TOUCH AND KINDLE PAPERWHITE

1. Tap the **Menu** button from the Home screen.
2. Select **Settings**.
3. Tap the **Menu** button again.
4. Select **Device Info**.
5. Scroll down to find the **Wi-Fi MAC** address.

BARNES AND NOBLE NOOK

1. Press the **Home** button.
2. Tap **Settings**.
3. Find the entry for MAC Address.

BARNES AND NOBLE NOOKCOLOR

1. Tap the **Nav Arrow** at the bottom of the screen to display the **Quick Nav Bar**.
2. Tap **Settings** then tap **Device Info**.
3. Tap **About Your NOOKcolor**.

4. Find the entry for MAC Address.

Media Players and DVRs

APPLE TV

1. Select **Settings**.
2. If you are using software version 1.x, select **About**. If you are using software version 2.0, select **General**, and then select **About**.
3. The MAC Address will be listed as either **Wireless ID** or **Ethernet ID**.
 - a. You can also find both the Wireless ID and Ethernet ID on the UPC label on the bottom or back of the Apple TV box, next to the serial number.

ROKU (NETFLIX) PLAYER

1. Select **Settings**.
2. Select **About**.
3. The Mac Address will be listed on-screen. a. You can also find the MAC addresses on the bottom or back of your Roku player.

TIVO

1. Press the **TiVo button** to go to **TiVo Central**.
2. Select **Messages and Settings**.
3. Select **Phone and Network Setup**.
4. The MAC address will be displayed at the top right-hand side of the screen.

BOXEE BOX

1. Select **Settings**.
2. Select **System**.
3. Select **Information**.
4. The MAC Address will be displayed on screen.

BOXEE TV

1. Select **Settings**.
2. Select **Network**.
3. The MAC Address will be displayed on screen.

GOOGLE TV

1. Select **Settings**.
2. Select **Network**.
3. Select **Status**.
4. The MAC Address will be displayed on screen.

Mobile Devices

ANDROID DEVICES

1. From the Home screen, press **Menu**.
2. Select **Settings**.
3. Select **About Phone** or **About Tablet**. a. In some cases, you may have to select **Wireless & Networks** first, and check the box marked **Wi-Fi** to turn the wireless on.
4. Select **Status**. (For some versions, you may need to select **Hardware Information** instead).
5. Scroll down to the **Wi-Fi MAC Address** field.

APPLE IOS DEVICES (IPHONE, IPAD, IPOD TOUCH)

1. Tap **Settings** from the Home screen.
2. Tap **General** and then tap **About**.
3. Your MAC Address will be listed as **Wi-Fi Address**.

BLACKBERRY DEVICES

1. Select **Options** from the home screen, and then select **Status**.
2. Your MAC address will be listed in the **WLAN MAC** field. a. Not all BlackBerry devices have Wi-Fi.

WEBOS DEVICES (PALM)

1. In the **Launcher**, scroll to the screen with the **Device Info** app and launch it.
2. Select **More Info**. (In some versions you will also need to select the **Hardware** tab.)
3. Your MAC address will be listed in the **Wi-Fi** section.

WINDOWS MOBILE DEVICE

1. Make sure your Wi-Fi is enabled.
2. Select **Start**.
3. Select **Settings**, and then select **Connections**.

4. Select **Wireless LAN** and then select the **Advanced Tab**.
5. Your MAC address will be listed in the **MAC** field. a. Alternatively, your device may have the MAC address listed under **Start>Settings>Wi-Fi Manager>Advanced**.

WINDOWS NOKIA LUMIA 900

1. Select **Settings**. Then, tap **About** and then tap **More Info**.
2. In the third tab, there will be a box for MAC address.

WINDOWS PHONE

1. In the **App List**, tap **Settings**.
2. Tap **About** and then tap **More Info**.
3. The Mac Address will be listed on this screen.

Portable Game Consoles

NINTENDO DS (AND LITE VERSION)

1. Start a game that has Wi-Fi capabilities.
2. Go to **Settings**.
3. Select **Nintendo Wi-Fi Connection Setup**. a. Also could be listed as **Nintendo WFC Setup**.
4. Select **Options**.
5. Select **System Information**.
6. Your MAC address will be displayed.

NINTENDO 3DS

1. Tap the wrench icon to access **System Settings**.
2. Tap **Internet Settings**.
3. Tap **Other Information**.
4. Tap **Confirm Mac Address**.
5. Your MAC address will be displayed on screen.

SONY PSP

1. Turn on the PSP without a game in the system.
2. Press the **Home** button.
3. Press **Settings**.
4. Press **System Settings**.
5. Press **System Information**.
6. Your MAC address will be displayed.

SONY PS VITA

1. From the home screen, tap **Settings**.
2. Tap **Start**.
3. Scroll up and tap the **System** option.
4. Tap **System Information**.
5. Your MAC address will be displayed on screen.

NINTENDO WII U

1. From the Wii U menu, select **System Settings**.
2. Use the left stick to select **Internet** and press the A button.
3. Select **View Mac Address** and wait for it to display.

Video Game Consoles

MICROSOFT XBOX ONE

The first time turning on an Xbox One system requires an internet connection to reach the settings menu which is where you will find the wired MAC address you need to register your device. The work around for this is to allow the Xbox to run through the system setup, let it fail, select "Fix It" and then it will attempt to diagnose the issue. When that fails, it will bring you to a screen prompting you to manually set up the connection, listing both the wireless and wired MAC address.

If you are able to reach the main menu on your Xbox, try the following to find the MAC Address.

1. Navigate to **My Games and Apps**.
2. Select **Settings**.
3. Select **Network**.
4. Select **Advanced Settings**.
5. The Wired and Wireless MAC address will be displayed to the right of your screen.

MICROSOFT XBOX 360

1. Select **System** from the Xbox Dashboard.
2. Select **Network Settings**.
3. Select **Edit Settings**.
4. Select **Additional Settings**.
5. Select **Advanced Settings**.

6. For Wired connections, your MAC address will be displayed under the heading Wired MAC Address. a. For Wireless connections, select **Wireless Information**. Your MAC address will be displayed on this screen.

For the new NXE display

1. Go to **My Xbox** on the Xbox Dashboard.
2. Select **System Settings**, all the way to the right.
3. Select **Network Settings**.
4. Select **Configure Network**.
5. Under the **Basic Settings** tab, make sure **IP Settings** is on **Automatic**.
6. Go to the **Additional Settings** tab.
7. Select **Advanced Settings**.
8. The MAC address is displayed on screen as **Wired MAC Address**.

NINTENDO WII

1. From the Wii menu, choose **Wii Options**.
2. Select **Wii Settings**.
3. Click right to **Wii System Settings 2**.
4. Select **Internet**.
5. Select **Console Information**.
6. You will find your MAC address on this screen.

NINTENDO WII U

1. Go to **System Settings**.
2. Tap the **Internet** settings button.
3. Select **View MAC Address**.
4. Your MAC address will be displayed.